

HMI Command List

Date:	2021/11/12	

Page 1 of 9

Ver. No.: V1.1

Document History

Ver. No.	Date	Revision History	Author(s)
V1.0	2021/09/22	Release the document.	Marco Yang
V1.1	2021/11/12	修正command 0x01,0x03文字敘述	James



HMI Command List

Date: 2021/11/12

Page 2 of 9

Ver. No.: V1.1

Table of Contents

- 1 Scop
- 2 Abbreviation
- 3 Architecture
- 4 Command Format
- 5 Command description
 - 5.1 0x00 Ping Request
 - 5.2 0x00 Ping Response
 - 5.3 0x01 Set Digital Output Request
 - 5.4 0x01 Set Digital Output Response
 - 5.5 0x02 Get IO state Request
 - 5.6 0x02 Get IO state Response
 - 5.7 0x03 Get RFID Data Request
 - 5.8 0x03 Get RFID Data Response



HMI Command List

Date: 2021/11/12
Page 3 of 9

Ver. No.: V1.1

1 Scop

This document describes the command of HMI to support IO control and RFID reader to meet locker requirements.

2 Abbreviation

UART	Universal Asynchronous Receiver/Transmitter
НМІ	Human Machine Interface




HMI Command List

Date: 2021/11/12

Page 4 of 9

Ver. No.: V1.1

3 Architecture





HMI Command List

Date: 2021/11/12
Page 5 of 9

Ver. No.: V1.1

4 Command Format

1. Request command: (Control side UART -> HMI UART)

	Tag ID	Length [1]	Cmd ID	Data [n]	CRC [1]
--	--------	------------	--------	----------	---------

2. Response command: (HMI UART -> Control side UART)

Tag ID	Length	Cmd ID	Data[n]	CRC [1]
[1]	[1]	[1]		

3. Indication command: (HMI UART -> Control side UART)

	Tag ID	Length [1]	Cmd ID	Data[n]	CRC [1]
--	--------	---------------	--------	---------	---------

4. Indication ack command: (Control side UART -> HMI UART)

Tag ID [1] Length [1]	Cmd ID [1] CRC [1]	
-----------------------	--------------------	--

CRC = 0 - Tag ID - Length - Cmd ID
Ex: Ping Request
CRC =
$$0x00 - 0xFC - 0x05 - 0x00 = 0xFF$$



HMI Command List

Date: 2021/11/12

Page 6 of 9

Ver. No.: V1.1

5 Command description

5.1 0x00 Ping Request

Control side UART -> HMI UART Used to test the communication is workable.

Tag ID [1]	Length [1]	Cmd ID [1]	CRC [1]
------------	------------	------------	---------

Tag ID	1 byte. Command UART Tag = 0xFC
Length	1 byte. Total message length = 4
Cmd ID	1 byte. Command Ping Request = 0×00
CRC	1 byte. CRC code

5.2 0x00 Ping Response

HMI UART -> Control side UART
Used to respond to the request command

Tag ID [1]

Tag ID	1 byte. Command UART Tag = 0xFD
Length	1 byte. Total message length = 4
Cmd ID	1 byte. Command Ping Response = 0×00
CRC	1 byte. CRC code



HMI Command List

Date: 2021/11/12

Page 7 of 9

Ver. No.: V1.1

5.3 0x01 Set Digital Output Request

Control side UART -> HMI UART Used to set the digital output to the HMI.

Tag ID [1]	Length	Cmd ID [1]	Data [n]	CRC [1]
	[_]			

Tag ID	1 byte. Command UART Tag = 0xFC
Length	1 byte. Total message length = 4 + n
Cmd ID	1 byte. Command Set Digital Output Request = 0×01
Data	n bytes. Value of the bitmap.
CRC	1 byte. CRC code

5.4 0x01 Set Digital Output Response

 $\ensuremath{\mathsf{HMI}}$ UART -> Control side UART Used to respond to the request command

Tag ID	1 byte. Command UART Tag = 0xFD
Length	1 byte. Total message length = 4 + 1
Cmd ID	1 byte. Command Set Digital Output Response = 0×01
Result	<pre>1 byte. 0 = Success. 1 = Fail.</pre>
CRC	1 byte. CRC code



HMI Command List

Date: 2021/11/12

Page 8 of 9

Ver. No.: V1.1

5.5 0x02 Get IO state Request

Control side UART -> HMI UART Used to get an IO state of HMI.

Tag ID [1] Length [1]	Cmd ID [1]	Data[1]	CRC [1]
-----------------------	------------	---------	---------

Tag ID	1 byte. Command UART Tag = 0xFC
Length	1 byte. Total message length = 4 + 1
Cmd ID	1 byte. Get IO status Request = 0×02
Data	1 byte. 0 = DI port. 1 = DO port.
CRC	1 byte. CRC code

5.6 0x02 Get IO state Response

HMI UART -> Control side UART
Used to respond to the request command

Tag ID [1]	Length	Cmd ID [1]	IO [1]		CRC [1]
	[1]			[n]	

Tag ID	1 byte. Command UART Tag = 0xFD
Length	1 byte. Total message length = 4 + 1 + n
Cmd ID	1 byte. Get IO status Response = $0x02$
IO	1 byte. 0 = input. 1= output.
Data	n bytes. IO Status data.
CRC	1 byte. CRC code



HMI Command List

Date: 2021/11/12

Page 9 of 9

Ver. No.: V1.1

5.7 0x03 Get RFID Data Request

Control side UART -> HMI UART Used to get the RFID Data.

Tag ID [1] Length [1] Cmd ID	.] Timeout [1]	CRC [1]
------------------------------	----------------	---------

Tag ID	1 byte. Command UART Tag = 0xFC
Length	1 byte. Total message length = 4 + 1
Cmd ID	1 byte. Command Get RFID Data Request = 0×03
Timeout	1 byte. Unit of a second.
CRC	1 byte. CRC code

5.8 0x03 Get RFID Data Response

HMI UART -> Control side UART
Used to respond to the request command

Tag ID [1] Length [1] Cmd ID [1]	Result [1]	Data [n]	CRC [1]
----------------------------------	------------	----------	---------

Tag ID	1 byte. Command UART Tag = 0xFD
Length	1 byte. Total message length = 4 + 1 + n
Cmd ID	1 byte. Command Get RFID Data Response = 0×03
Result	1 byte. Result data. 0 = Pass. 1 = Fail.
Data	n bytes. RFID Content of the key or ID.
CRC	1 byte. CRC code